



# KEGEL LANDMARK PATTERNS





# KEGELLANDMARK PATTERNS

# **SPORT SERIES**



### ALCATRAZ 2038

38' patterns can often handcuff players because they are too short to play inside, but too long to play outside. However, within the Alcatraz oil pattern there looks to be an escape route, and many have tried to use it, but very few have succeeded.

### **Latitude Ratio Coordinates**

22' 2.0 to 1 36' 1.5 to 1

### **Longitude Ratio Coordinates**

Outside Taper 5.8 to 1 Inside Taper 6.3 to 1

#### **Pattern Distance**

38 Feet

#### **Pattern Volume**

Forward 13.695 mL Reverse 11.150 mL Total 24.845 mL



# KEGELLANDMARK PATTERNS


## **SPORT SERIES**



### ALCATRAZ 2038

### **Latitude Ratio Coordinates**

8' 1.6 to 1 14' 2.5 to 1 22' 2.0 to 1 27' 2.1 to 1 32' 1.7 to 1



The 2D Chart above was generated by the Lane Reader showing select tapes and ratios at key distances throughout the oil pattern. USBC Sport Bowling ratios are calculated at 22' and 2' before the end of the oil pattern. **KEGEL KODE Ratios** are determined by the highest Sport Bowling ratio number for that oil pattern.

**KEGEL TIP** - Generally, the lower the ratios towards the end of the oil pattern, the less guidance of the bowling ball and therefore, the more difficult the oil pattern may play. The higher the ratios are towards the end of the oil pattern, the easier it may play.



# KEGELLANDMARK PATTERNS

## **SPORT SERIES**



This page shows the **KOSI FLEX LANE MACHINE** program sheet.

The **HEADER** shows the oil pattern distance, the reverse brush drop distance, the amount of lane conditioner applied to the lane, the oil per board setting, and the conditioner type in each tank.

Below that is the **FLEX LANE MACHINE PROGRAM** settings which shows the load structure and number of loads, the oil pump setting if using the multi mic stream feature, the speed of the lane machine, the buffer speed, and the tank choice per load screen.

The **OVERHEAD CHART** on the far right shows where the conditioner is applied on both the forward and reverse pass. The gradient area is a calculation of how the conditioner might bleed off the buffer brush.

The **COMPOSITE GRAPH** at the bottom shows the total amount of conditioner applied to every board along with that volume ratio in different zones.

A good way to think about the composite graph is to envision all the conditioner on the lane being pushed back to the foul line. Once all the conditioner is stacked up, this is what it would look like.



#### S - Alcatraz



Oil Pattern Distance	38	Reverse Brush Drop	38	Oil Per Board	Multi ul
Forward Oil Total	13.695 mL	<b>Reverse Oil Total</b>	11.15 mL	<b>Volume Oil Total</b>	24.845 mL
Tank Configuration	N/A	<b>Tank A Conditioner</b>	FIRE	<b>Tank B Conditioner</b>	ICE

	START	STOP	LOADS	MICS	SPEED	BUFFER	TANK	CROSSED	START	END	FEET	T.OIL
1	2L	2R	5	45	14	3	В	185	0.0	7.9	7.9	8325
2	6L	6R	2	45	14	3	В	58	7.9	11.8	3.9	2610
3	8L	8R	1	40	18	3	В	25	11.8	14.3	2.5	1000
4	9L	9R	1	40	18	3	В	23	14.3	16.8	2.5	920
5	10L	10R	1	40	18	3	В	21	16.8	19.3	2.5	840
6	2L	2R	0	40	18	3	В	0	19.3	32.0	12.7	0
7	2L	2R	0	40	30	2	В	0	32.0	38.0	6.0	0

	START	STOP	LOADS	MICS	SPEED	BUFFER	TANK	CROSSED	START	END	FEET	T.OIL
1	2L	2R	0	40	30	1	В	0	38.0	34.0	-4.0	0
2	17L	17R	3	40	18	3	В	21	34.0	26.4	-7.6	840
3	10L	10R	1	40	18	3	В	21	26.4	23.9	-2.5	840
4	9L	9R	1	40	18	3	В	23	23.9	21.4	-2.5	920
5	8L	8R	2	45	18	4	В	50	21.4	16.3	-5.1	2250
6	6L	6R	1	45	18	4	В	29	16.3	13.8	-2.5	1305
7	2L	2R	3	45	14	4	В	111	13.8	7.9	-5.9	4995
8	2L	2R	0	45	14	4	В	0	7.9	0.0	-7.9	0

Cleaner Ratio Main Mix 4:1
Cleaner Ratio Back End Mix 4:1
Cleaner Ratio Back End Distance 59
Buffer RPM: 4 = 700 | 3 = 500 | 2 = 200 | 1 = 60

-	ı					ı				ľ					ľ																										ļ	
t	ŀ	ł	1		ŀ	l	1			ŀ	1				ŀ	ł	1				ŀ	ŀ	ł	ł	1	1						ŀ	ł	ŀ	ł	ł	ł	$\dagger$	1	ł	t	55
													- 3																	-												
	Ī	Ī				Ī	1	8		Ī					Ī	I	I		all a	600	Ī	Ī	Ī	I	I		100	80					Ī		I	I	Ī	Ī	Ī	Ī		2
+		1			-			2								+	1		2	-	-	-	1	1	1	-			ŀ			-	ŀ	-		+	1	+	+	+	ļ	55
l	l	l				l	l			l	l					l	l					l	l	l	l	l				l				l	l	l	l	l	l	l	l	
t	ł	t				l	1			l				L		ł							ł	t	1							ŀ	ŀ		ł	ł	t	1	+	1	t	8
																							l																			, s
	l	l										i				I	ı	•		8			l	١	۱											I	I	I	I	I		
+	ŀ	1				ŀ				ŀ						ł				ŀ	ŀ	ŀ	ł									ŀ	-		ŀ	ł	1	1	1	1	+	s
	l	l	ı	ı	l	l	ı	ı		l					l	l	ı						l	l	I									l	l	l	l	l	ı	ı	ı	
t	t	t			ŀ	ł	ı		۱	l				ŀ	ł	t	ı				ŀ	l	t	t	t	1					ŀ	ŀ	ŀ	l	t	t	t	t	t	t	t	×
	l					l				l					L	l							l		l									l		l	l					١
	l	l			ľ											ı							ı	ı	I										I	l	l	l	I	l		1
						ŀ										ł							l	ł	ł									ŀ								4
ı	l	l																																		l	l	l	l	l	ı	
																																				l			1			=

Item	3L-7L:18L-18R	8L-12L:18L-18R	13L-17L:18L-18R	18L-18R:17R-13R	18L-18R:12R-8R	18L-18R:7R-3R
Description	Outside Track:Middle	Middle Track:Middle	Inside Track:Middle	Mlddle: Inside Track	Middle:Middle Track	Middle:Outside Track
Track Zone Ratio	2.19	1.23	1.12	1.12	1.23	2,19
1500 -						
1200						
1350						
1350 —						
1350			a.I.I.I.I.			
1350			711111		Hana	
1350						
1350						

**KEGEL TIP** - Once the amount of conditioner on the corners (outsides) reaches 300 microliters, an oil pattern begins to become "competitive". Less than that amount the ball might see friction and it could play on the easy side.